

Margaret Moorehead's

Virtual Sewing Guild OnLine Class

Wine Bagette



Supply List:

- * Fabric for Bagette
- * Pocket Fabric
- * Thermal Insulated Batting
- * 1 Pair Purse Handles 6 1/2" x 5"
- * Grosgrain Ribbon 1 1/2" wide
- * 1/4" wide roll of fusible web
- * Fusible Interfacing
- * Cardboard or canvas panel
- * Bagette Templates by Margaret Moorehead (supplied with this class)
- * Glue Stick
- * Fray Seam Sealant
- * Needles: Regular
- * 2 Zippers: 9" or longer* 1 Zipper15" or longer

Equipment List:

- * Embroidery Machine in good working order
- * Size 80 needle for general construction
- * Size 80 or 90 needle to stitch through cardboard
- * General Sewing Supplies
- ***** Zipper foot
- * Open. Toe Foot
- * Edge stitch or stitch in the ditch foot

Note:

These instructions are to be used in conjunction with the video for this class.

Printing the templates

The pattern pieces/templates for this project are in a zipped file. Please "unzip" the file and print out the correct number of templates. Measure the printed template to see if it printed at the required size. If not, reprint adjusting your printer settings and print again, measure and repeat until it is at the correct size.

Virtual Sewing Guild: Wine Bagette

Fabric and Batting	Quantity	size	prep
Bagette Fabric	1/2 yard	45" wide fabric	Print templates and cut out of fabric
Pocket Fabric	2	8" h x 11" w	
Thermal Insulated lining	1/2 yard		Print templates and tape together, then cut out insulated batting
1 1/2" wide Grosgrain Ribbon	1	15"	See Video
Fusible interfacing	8	3" x 2" squares	
	2	3" x 11" rectangles	
Cardboard or Canvas Panels	1	*may vary for your project but should be: 3 1/"2 x 13 1/2"	Do not cut until your Bagette is to this point in construction

All designs, instructions and videos are the sole property of MKKB Enterprises





Virtual Sewing Guild: Wine Bagette

Getting Ready

- 1. Print the Pattern Templates, being sure that the measurements printed on your templates are the size that your templates actually measure. Note: you will need to print 4 of the insulated batting template.
- 2. Cut out the templates and cut out the bagette pieces
- 3. Tape the 4 insulated batting templates together and then cut out one "lining" piece from the thermal insulated batting, using the taped together template.
- 4. This project uses 1/2" seam allowances unless otherwise indicated

Hint: test your marking pencil or marker by ironing over it and then making sure the marks will still disappear

Marking

- 1. Bagette Bottom:
 - 1. Mark vertical center
 - 2. Measure up 1/2" from the bottom and in 1/2" from the side and mark with a dot. Do this for all 4 corners.
- 2. Pocket
 - 1. Mark vertical center
 - 2. Measure down 4 1/2" from top of pocket and draw a line that extends 4" to to the right of center and 4" to the left of center
 - 3. Using the line you just drew, measure down 3/8" and draw a line parallel to that, connect these two lines at the right and left. This your your stitching line for the inset zipper
 - 4. Do this on both the front and back of each pocket
- 3. Bagette Sides:
 - 1. Mark the vertical center on right and wrong size of both bagette side pieces
 - 2. One the right side of the fabric, measure down 2 1/2" from the top and draw a line that extends 4" to the right of the vertical center and 4" to the left of the vertical center.
 - 3. Using the line you just drew measure down 3/8" and draw a line that is parallel to this line, connect these two lines at the right and left.

Virtual Sewing Guild: Wine Bagette

Wine Bagette

Marking Continued....

- 4. Mark the back of the bagette fabric in the same manner
- 5. Mark the bottom corners of the bagette sides 1/2" in from the sides and 1/2" up from the bottom. Do this on both the bottom corners.

Zipper Insets/pockets.

(Note: this process will need to be done for both sides of the bagette)

- 1. Fuse the 3" x 11" interfacing pieces to the back side of the bagette side pieces so it is centered over the marked lines.
- Put the right side of one of the bagette pieces to the right side of one of the pockets, lining up the marked lines, making sure that the pocket is positioned so the bottom of the pocket does NOT extend beyond the bottom of the bagette, and DOES extend beyond the top of the bagette
- 3. Pin in place
- 4. Stitch on marked line using a stitch length of 1.5, and an open toe foot, pivoting at the corners.
- 5. Use fray seam sealant on the short lines of the rectangle, and iron dry
- 6. Iron your project to make sure everything is positioned correctly and to set your stitches.
- 7. Cut down the center of the rectangle through the bagette fabric and pocket fabric. Stop cutting about 1/2" before the end of the rectangle and cut towards each corner to form a "Y" cut.
- 8. Be sure to cut all the way to the corner, but not through the corner.
- 9. Pull the pocket through the cut opening and press the project so the pocket fabric will now be on the back side of the bagette
- 10. Press this area so it looks nice
- 11. Position the zipper under the opening right side up making sure the zipper is closed and the pull is all the way up to one end of the opening

Wine Bagette

- 12. If you have used a "longer" zipper measure how long you need it to be, mark with a pin, and zig zag over the coils of the zipper to form a "stop" for your zipper, then cut off the excess zipper tape.
- 13. Fuse the 1/4" fusible web to the right side of the zipper tape on each edge, then remove the protective paper.
- 14. Position the zipper in the opening you created making sure it is centered in the opening, and the zipper pull is all the way to the end of the rectangle and the pocket is positioned correctly.
- 15. Fuse in place
- 16. Use the zipper foot and adjust the needle position so your stitching will line up in a way that is pleasing to you and stitch around the opening to attach the zipper.
- 17. Open the zipper when needed to be able to keep your stitching very straight and professional looking.
- 18. Fold the pocket from the top down so the bottom raw edges line up, and stitch down both sides and across the bottom to create the pocket

Top Zipper

- 1. Position the bagette pieces so they are right side up in front of you, with the top sides close to each other, and the zipper between them.
- 2. Fold down the top side of one bagette piece as it will look when it is stitched, then flip the bagette piece over the zipper so the right side of the zipper is touching the right side of the bagette and the edge of the zipper tape is lined up with the cut edge of the top of the bagette.
- 3. Stitch in place using the narrow edge foot (stitch in the ditch foot) positioning the needle so the stitching will be at a width that is pleasing to you.
- 4. When the first side is finished position the two pieces of the bagette in front of you again right side up and zip the zipper closed.
- 5. Fold under the raw edge of the top of the other bagette piece and then flip the bagette piece over so you have right sides together and have the side cut edges lined up, and the raw edge of the top of the bagette with the edge of the zipper tape. Then stitch in place. (Please refer to video if needed)

Bottom and side seams

- 1. Pin the pockets up towards the top to keep them out of the way
- 2. Line up one long edge of the "bottom" piece with the bottom edge of the bagette, making sure the center vertical lines match.
- 3. Stitch these together starting 1/2" in from the bottom piece of the bagette and ending 1/2" from the other side of the bagette bottom. Note: you will not be stitching all the way across the bottom of the bagette pieces that have the pockets in them. You will stop at the marks we made earlier on the "Bottom" piece.
- 4. Repeat for the other side
- 5. Iron the seams and unzip the zipper at the top of the bag so you will be able to get into the bagette once the sides are stitched.
- 6. Line up the side seams of the bagette and stitch from the zipper at the top down to the bottom of the side seam on both sides.
- 7. Press the seams as they were stitched and then press them open. (I use my pressing board for this)
- 8. Stitch the bottom of the bagette to the sides of the bagette. To do this you will need to clip the bagette (not the bottom) from the bottom cut edge up to but not through the stitching that holds the bottom of the bagette to the bagette pieces that have the pockets in them. By clipping this fabric your project will line up correctly so you can stitch the sides to the bottom.
- 9. Turn right side out

Cardboard at bottom

- 1. Cut your cardboard to 3 1/2" x 13 1/2" or whatever size. You need for your project.
- 2. Position in the bottom of the bag making sure it lines up correctly and stitch in place along each side using a size 90 needle and a long stitch length.
- 3. You will not be able to stitch all the way to each end, so just stitch as far as you can on each side and tie off at the beginning and end each time.

Handles

- 1. Mark the placement of your handles by measuring the width of your handles and determining the placement above the zipper pocket and below the zipper at the top of the bagette. Mine was 1 3/8 inches down from the top and 3 1/4" to each side of the center.
- 2. Fuse 1/4" fusible web to each long edge of the grosgrain ribbon.
- 3. Mark a line down the center of the ribbon.
- 4. Fold the edges into the center line and press in place
- 5. Stitch down the center with a zig zag or simple decorative stitch.
- 6. Cut into pieces that are 3" in length.
- 7. Mark up from one side (bottom) 1/2", apply glue from a glue stick to that area, fold up and iron dry
- 8. Mark down 1" from the other edge (top) and finger press a crease into the ribbon
- 9. Slip the top of the ribbon through the ring of the handle, fold down the ribbon on the crease and glue the bottom of the ribbon in place.



- 10. Pin and stitch in place on the purse, using an open toe foot.
- 11. Cut off excess zippers from inside of the bagette if needed

Insulated Lining

- 1. Fold in half right side together and stitch along each side edge.
- 2. Fold the lining to form a "box" corner, line up the raw edges and stitch each corner.
- 3. Insert the lining into the bagette, wrong sides together, and make sure it is positioned nicely,
- 4. Fold down the top edge of the insulated batting/ling and pin along the top edge then stitch in place. Note: you will not be able to stitch all the way to the side seams on the sides, this part will need to be hand stitched.
- 5. Hand stitch to complete and ENJOY!