

Pickle PieTM

DESIGNS

Single Block Wall Hanging Project Guide



Remember: Complete the stitching instructions for each chosen block up to the red **STOP** notation. You'll then come back to these projects to finish the project.

Additional Supplies you'll need...

- Fabric for Back, Fat Quarter
- 14" length of Grosgrain Ribbon, 7/8" or wider
- 1" Fusible Seam Tape

All measurements are listed width x length.


Prep your fabrics...

Cut Fabric...

	Label	8" Block	7" Block	6" Block	5" Block	4" Block
Back piece 1	1	10" x 4"	9" x 4"	8" x 4"	7" x 4"	6" x 4"
Back piece 2	2	10" x 10"	9" x 9"	8" x 8"	7" x 7"	6" x 6"

Other Fabric Prep...

- Fabric 1: fold back 1" lengthwise, wrong sides together. Press.




- Fabric 1: Press fusible seam tape along the right side of the fold, as shown. Leave any paper backing on the tape intact for now.




You should have your first block completed until the red **STOP** in the block instructions. **Leave the project hooped** and follow the steps below...

1. Remove the hoop from your machine, but leave the project in the hoop. Carefully remove any tape around the project.

Using a ruler and pen, measure down 2" from the top left stitch line. Mark this outside the left stitch line as indicated by the arrow in the picture.




2. Repeat on the right side, marking 2" down from the top stitch line and marking outside the stitch line.




3. Measure 1" from the left stitch line. Mark this outside the top stitch line as indicated by the first arrow in the picture.

Repeat on the right, marking where indicated by the right arrow in the picture.




4. Place one end of ribbon 1/2" over the top left stitch line. Align the left edge of the ribbon with top line you drew in step 3. Tape in place above the top stitch line.


Repeat with the remaining ribbon on the right side of the block.




5. If your ribbon extends near or over the bottom edge of the project, fold it up to the center and tape to prevent it from getting caught in the bottom seam.



6. Place Fabric 1 over the top of the project, right side down, with the fold facing the center of the hoop. Align the fold just above the lines you drew in steps 1 and 2. Tape in place along the raw edges.




7. Place Fabric 2 over the bottom of the project, right side down, with the top edge overlapping Fabric 1 by 1". Tape in place on the sides and lower edge.




8. Put the hoop back on your machine.

Sew the final stitch sequence to stitch the layers together.



9. Remove the hoop from your machine and take the project out of the hoop. Remove the tape.

Trim around the project, leaving a 1/2" seam allowance, and clip the corners.



10. Turn the project, right side out, through the opening in the back.

Pull off any paper backing on the seam tape. Iron the back of your project over the opening to allow the seam tape to fuse it closed.



11. Press the rest of the project to complete, being careful not to iron your ribbon.



You're done!